[New Exam Dumps PassLeader New 77q 3204 Exam Questions with Free PDF Study Guide Download

Want To Pass The New 3204 Exam Easily? DO NOT WORRY! PassLeader now is supplying the latest and 100 percent pass ensure version 77q 3204 PDF dumps and VCE dumps, the new updated 3204 braindumps are the most accurate with all the new changed questions, it will help you passing 3204 exam easily and quickly. Now visit the our site passleader.com and get the valid 77q 3204 VCE and PDF exam questions and FREE VCE PLAYER! keywords: 77q 3204 exam dumps,3204 pdf dumps,3204 braindumps,3204 vce dumps,77q 3204 exam questions,3204 practice test,Avaya Aura Conferencing Implementation and Maintenance Exam



QUESTION 10f the three Media Server roles, which Role is used to prompt for conference codes? A. IVRB. HostingC. CascadingD. ANNC Answer: AExplanation:

http://portaone.com/resources/docs/PortaSIP/m-r-45/PortaSIP Media Server MR45.pdf (See the Page #8, 1ST Paragraph). QUESTION 2Under which condition will a redundant conferencing application server failover? A. If the active Avaya Aura Conferencing database is unreachableB. If the Media Server is unreachableC. If the firewall blocked the signaling serverD. If the primary application server stops communicating with the standby application server Answer: A QUESTION 3What is the script that is used to install Avaya Aura Conferencing software? A. InstallmcpB. pkginstallC. aaclnstallerD. mcplnstaller Answer: DExplanation: Avaya Media Server: The Avaya Aura Conferencing application requires one or more Avaya Media Servers for media processing. The mcpInstaller script can install the media server automatically in all (SMB, medium, and large) configurations. If you are implementing a redundant deployment, the mcpInstaller automatically installs a primary and a secondary Avaya Media Server. https://downloads.avaya.com/css/P8/documents/100182326 QUESTION 4You are installing the operating system for Avaya Aura Conferencing and you turn on the hardware to start the installation. What must you then do at the boot prompt? A. type startinstall B. press the Enter keyC. type install-kvm and press the Enter keyD. type install-mcp and press the Enter key Answer: C Explanation:1. Insert the AAC Platform DVD-ROM, and reboot the server. The following message on the installation welcome screen appears: Welcome to the MCP Core Linux System Installer.2. At the boot prompt, type install-kvm, and press Enter.3. To check the integrity of the system, type y, and press Enter. https://downloads.avaya.com/css/P8/documents/100182326 QUESTION 5 Where can you modify the alert threshold settings for the Avaya Aura Conferencing? A. Monitoring and ReportingB. Key Performance IndicatorsC. OAM ProfilesD. Feature Server Elements Answer: BExplanation:

https://downloads.avaya.com/css/P8/documents/100182324 (See the Page #50). QUESTION 6What does the extension .active at the end of the log file name indicate? A. The log is currently closed.B. The log is the most recent log file.C. The log has been previously opened.D. The log is obsolete. Answer: BExplanation:Alarms are available to be viewed on the command line in /var/mcp/oss/log/EM/all/MCP/network element directory. The file that ends in .active is the most recent log file. The same information that was in the log browser is available in the command line log files. QUESTION 7You want to find the thresholds configured in the system for minor, major, and critical alarms for Jitter (ms) on the Element Manager. Under which folder are the Alert Thresholds found? A. Log FiltersB. Media Servers and ClustersC. Key Performance IndicatorsD. Application Servers Answer: A Why Not Try Possl ender New Premium 3204 Exam Dumps?

Why Not Try PassLeader New Premium 3204 Exam Dumps?



http://www.passleader.com/3204.html